


# Zerobyte (Restic Backup UI)



<https://github.com/nicotsx/zerobyte>

```
services:
  zerobyte:
    image: ghcr.io/nicotsx/zerobyte:v0.22
    container_name: zerobyte
    restart: unless-stopped

# -----
# OBACHT wenn man Volumes (zu speichernde Daten) oder Repositories (Ziele der Backups) mit SMB
# oder SFTP mounnten möchte,
# dann folgende Optionen:
  cap_add:
    - SYS_ADMIN
    - SYS_PTRACE
  security_opt:
    - seccomp:unconfined
    - apparmor:unconfined
```

```
# falls SFTP oder SMB nicht notwendig, dann nur:
  cap_add:
    - SYS_ADMIN
# -----

  ports:
    - "4096:4096"
  devices:
    - /dev/fuse:/dev/fuse
  environment:
    - TZ=Europe/Berlin # Set your timezone here
  volumes:
    - /etc/localtime:/etc/localtime:ro
    - app:/var/lib/zerobyte
    - /var/lib/docker:/backup-var-lib
    - /root:/backup-root-home
    - /mnt/fn-volume-01:/backup-fn-volume-01
    - /mnt/fn-volume-02:/backup-fn-volume-02

volumes:
  app:
```

# Hetzner S3 Object Storage als Repo

Backend: S3

Endpoint:

fsn1.your-objectstorage.com

Bucket: <Bucket-Bezeichnung-aus-Hetzner>/<gewuenschter-Unterordner> zb  
BUCKETNAME/Server-01

Acces-Key & Secret-Key aus Hetzner entnehmen

### Name

[REDACTED]/fn-02

Unique identifier for the repository.

### Backend

S3 ▾

Choose the storage backend for this repository.

### Compression Mode

Auto (fast) ▾

Compression mode for backups stored in this repository.

**Import existing repository**

Check this if the repository already exists at the specified location

### Endpoint

fsn1.your-objectstorage.com

S3-compatible endpoint URL.

### Bucket

[REDACTED]/fn-02

S3 bucket name for storing backups.

### Access Key ID

38v [REDACTED] 5XQ

S3 access key ID for authentication.

### Secret Access Key

.....

S3 secret access key for authentication.

### ▾ Advanced Settings

---

Revision #6

Created 2026-01-16 21:35:24 UTC

Updated 2026-01-23 22:03:24 UTC