

input.conf (Keyboardlayout us altgr-intl)

<https://wiki.hypr.land/Configuring/Variables/#input>

<https://learn.omacom.io/2/the-omarchy-manual/67/faq#how-do-i-switch-between-keyboard-layouts>

<https://learn.omacom.io/2/the-omarchy-manual/78/keyboard-mouse-trackpad>

Tastaturlayout: US-International für QWERTY aber trotzdem Umlaute zb mit

AltGr+Z = Ü

AltGr+Q = Ä

AltGr+P = Ö

https://de.wikipedia.org/wiki/Tastaturbelegung_US-International

~	! 1	@ 2	# 3	\$ £ %	^	&	* 1/4	()	-	+ ÷	←
1 i	2 2	3 3	4 x	5 €	6 1/4	7 1/2	8 3/4	9 ' 0 ' - ¥	= ×	Backspace	
Tab ←	Q Ä	W Å	E É	R	T P	Y Ü	U Ú	I Í	O Ó	P Ö	{ } ;
↔				®					[«] »	\ _
Caps Lock ↑	A Á	S Š	D Đ	F	G	H	J	K	L Ø	:	Enter ↵
		B							;	¶	↵
Shift ↑	Z Æ	X	C ç	V	B	N Ñ	M	< Ç	>	?	Shift ↵
			©				μ	,	.	/ ¿	
Ctrl	Win Key	Alt						Alt Gr	Win Key	Menu	Ctrl

In omarchy Win+Alt+Leertaste > Setup > Input

oder

`nvim .config/hypr/input.conf`

```
# Control your input devices
# See https://wiki.hypr.land/Configuring/Variables/#input
input {
    # Use multiple keyboard layouts and switch between them with Left Alt + Right Alt
    # kb_layout = us,dk,eu
    # alt-intl = International without dead-keys
    kb_layout = us
```

```
kb_variant = altgr-intl
kb_options = compose:caps # ,grp:alts_toggle

# Change speed of keyboard repeat
repeat_rate = 40
repeat_delay = 250

# Start with numlock on by default
numlock_by_default = true

# Increase sensitivity for mouse/trackpad (default: 0)
# sensitivity = 0.35

touchpad {
    # Use natural (inverse) scrolling
    # natural_scroll = true

    # Use two-finger clicks for right-click instead of lower-right corner
    # clickfinger_behavior = true

    # Control the speed of your scrolling
    scroll_factor = 0.4

    # Enable the touchpad while typing
    # disable_while_typing = false

    # Left-click-and-drag with three fingers
    # drag_3fg = 1
}
}

# Scroll nicely in the terminal
windowrule = match:class (Alacritty|kitty), scroll_touchpad 1.5
windowrule = match:class com.mitchellh.ghostty, scroll_touchpad 0.2

# Enable touchpad gestures for changing workspaces
# See https://wiki.hyprland.org/Configuring/Gestures/

# Enable touchpad gestures for changing workspaces
# See https://wiki.hyprland.org/Configuring/Gestures/
```

```
gesture = 3, horizontal, workspace
```

```
gesture = 3, vertical, dispatcher, togglespecialworkspace, scratchpad
```

```
gesture = 4, vertical, dispatcher, fullscreen, 1
```

Möglichkeiten:

```
cat /usr/share/X11/xkb/rules/evdev.lst
```

```
~ ) cat /usr/share/X11/xkb/rules/evdev.lst | grep intl
us-intl      ml: English (Mali, US, intl.)
intl         by: Belarusian (intl.)
qwerty       cm: Cameroon Multilingual (QWERTY, intl.)
azerty       cm: Cameroon (AZERTY, intl.)
dvorak       cm: Cameroon (Dvorak, intl.)
intl         gb: English (UK, intl., with dead keys)
mac_intl     gb: English (UK, Macintosh, intl.)
intl         us: English (US, intl., with dead keys)
alt-intl     us: English (US, alt. intl.)
altgr-intl  us: English (intl., with AltGr dead keys)
dvorak-intl  us: English (Dvorak, intl., with dead keys)
dvorak-alt-intl us: English (Dvorak, alt. intl.)
workman-intl us: English (Workman, intl., with dead keys)
us_dvorak    se: Swedish (Dvorak, intl.)
intl         tr: Turkish (intl., with dead keys)
```

```
~ ) █
```

Revision #6

Created 2026-02-24 23:00:55 UTC

Updated 2026-03-29 20:03:03 UTC