

Rustdesk

Anleitung

<https://rustdesk.com/docs/en/self-host/rustdesk-server-oss/docker/>

<https://integrations.goauthentik.io/integrations/services/rustdesk-pro/>

Ports öffnen

Be sure to open these ports in the firewall:

- `hbbs`:
 - `21114` (TCP): used for web console, only available in `Pro` version.
 - `21115` (TCP): used for the NAT type test.
 - `21116` (TCP/UDP): **Please note that `21116` should be enabled both for TCP and UDP.** `21116/UDP` is used for the ID registration and heartbeat service. `21116/TCP` is used for TCP hole punching and connection service.
 - `21118` (TCP): used to support web clients.
- `hbbr`:
 - `21117` (TCP): used for the Relay services.
 - `21119` (TCP): used to support web clients.

If you do not need web client support, the corresponding ports `21118`, `21119` can be disabled.

docker-compose.yml (free plan)

```
services:
  hbbs:
    container_name: rustdesk-hbbs
    image: rustdesk/rustdesk-server:1.1.14
#   environment:
#     - ALWAYS_USE_RELAY=Y
    command: hbbs
```

```
volumes:
  - app:/root
network_mode: "host"
depends_on:
  - hbbr
restart: unless-stopped

hbbr:
  container_name: rustdesk-hbbr
  image: rustdesk/rustdesk-server:1.1.14
  command: hbbr
  volumes:
    - app:/root
  network_mode: "host"
  restart: unless-stopped

volumes:
  app:
```

docker-compose.yml (pro plan, 20€ mit OIDC und Webconsole)

einfach

```
image: rustdesk/rustdesk-server:1.1.14
```

mit

```
image: docker.io/rustdesk/rustdesk-server-pro:1.6.1
```

ersetzen

Rustdesk-Console unter `http://<rustdesk-server-ip>:21114` erreichbar.
The default administrator username/password is `admin`/`test1234`:

OIDC (Pro-only)

<https://integrations.goauthentik.io/integrations/services/rustdesk-pro/>

Revision #6

Created 2025-06-26 09:36:15 UTC

Updated 2025-06-30 11:31:55 UTC